


Issue #1: Microsoft Visual Basic Error When Using BioVapor with Excel 2010

Detailed Description of the Problem

The starting the BioVapor software or while navigating the user interface, the following error is then generated:




The error “Run-time error ‘5’: invalid procedure call or argument” may also appear. In addition, the computer may freeze and it may be necessary to restart Microsoft Excel.

Cause


This error is caused by an incorrect reference in the Visual Basic compiler.

Solution

This problem can be resolved by setting the reference to the “Microsoft Windows Common Controls 6.0 (SP6)” Object Library. To do this, go to “the “Tools Menu” in the Visual Basic Editor (or hit ALT+F11 to get there from Excel).



This will bring up a dialog box showing all of the available libraries. You may have to scroll down a bit to find the specified library. Below is an example screenshot:



After making sure the check is in the appropriate box, click “OK” in the references window. Close the Visual Basic Editor and close and reopen Excel. The BioVapor software should now operate properly.